

# Routing custom products

New products will default to use the Hotfolder driver for printing. If you would like to route them differently, you will need to add the products to your apmconfig\_products\_custom.xml file on Lab 50, then use the Setup Wizard on Lab 50 to configure routing. To configure this file...

1. In Notepad (or better, Notepad++), open apmconfig\_products\_custom.xml (located in C:\Program Files\Lucidiom Lab 50\Tools\PrintServer). If this file does not yet exist, open a new file, and from apmconfig\_products.xml, copy top two lines of the apmconfig\_products.xml and the bottom line into a new xml file and save it as apmconfig\_products\_custom.xml. It will look like this (the order of the items doesn't matter. To check that you didn't screw up something, you should be able to open this file in a browser...if you have made any mistakes in syntax or formatting, it will show you where to fix.:

Print product:

```
<?xml version="1.0" ?>
<products units="all">
<product name="4x6 Fancy Print" description="4x6 Fancy Print" width="6000in" height="4000in" minwidth="
800" minheight="530" position="9003" id="9003" type="1" />
</products>
```

Creative products

```
<?xml version="1.0" ?>
<products units="all">
<product width="12000in" minheight="0" position="9000" height="12000in" description="12x12 12-Month
Calendar" id="9000" minwidth="0" package_type="calendar"/>
</products>
```

2. Replace the ID and position code with the same product ID used for your product. If you are using a duplicated product ID, you should instead use the Fulfillment ID field which will serve as a fake Product ID for the purposes of fulfillment. You should use a unique number in the 9000-9999 block. The product ID and position code should use the same number. Don't repeat a number you have already used.
3. Save as apmconfig\_products\_custom.xml in the same folder location where the apmconfig\_products.xml is located, which for a Lab 50 machine is C:\Program Files\Lucidiom Lab 50\Tools\PrintServer
4. Configure as needed in Lab 50's Setup Wizard. (Settings > Fulfillment > Print Server)

homeordersmembersstore managementaccount managementtemplate editorsettings

Tasks

▶ Save and exit

▶ Apply changes

▶ Export settings

▶ Import settings

▶ Back

Preferences

▶ Environment

▶ Order Management

▶ Photo Processing

▲ Fulfillment

General

➤ Print Server

EQ Gifting

Output Folder

Disk Maker

Back Lab Bumer


Media Manager

Adobe PDF

▶ Reporting

▶ Diagnostics

Fulfillment \ Print Server

Print Server hot folder:

C:\APM\_TRANSFER\orders\local

☒ Start the PrintServer automatically

☐ Fit photos to paper

APM Setup Wizard...