

Chapter 2 - Configuring Lab to Process APM Orders

In order to process APM orders through Lab 50, you will need to make configuration changes at both the APM and Lab 50.

The initial steps are the following:

1. In the APM software, one or more fulfillments must be set to process via Lab 50 on a local network or using APM Order Agent.
2. On the APM machine, the folder path **C:\APM_TRANSFER\Orders\local** must be shared with permission for network users to change/modify files.
3. In Lab 50, the import folder location must be specified for each kiosk that will be sending orders to it for processing in-store, or if the kiosk is remote, the ID must be setup as a remote kiosk import.
4. In Lab 50, the printer configuration must be specified for each product that will be processed from the kiosk.

[Chapter 2 - Table of Contents](#)